## USB INSTALLATION GUIDE

Use these instructions to install the Microsoft® Windows® printer driver for the Monarch® Sierra Sport4<sup>™</sup> 9493<sup>™</sup> printer and send data to the USB port. These instructions are written for Microsoft® Windows® XP. You must have a USB port and the proper cable to connect the printer to your computer.

## Connecting the Printer

Use these instructions to connect the printer to the computer's USB port before installing the printer driver.

- 1. Use the designated USB cable to connect the USB port on the printer to the USB port on your computer. Refer to the *Operator's Handbook* available on the Monarch® Documentation CD-ROM included with your printer for more information.
- 2. Turn on the printer.

The computer acknowledges the new hardware.

## Installing the Printer Driver

Use these instructions to install the 9493 printer's Windows printer driver.

Note: The screens may appear differently on other Microsoft® Windows® versions.

- 1. Insert the *Monarch® Printer Documentation CD-ROM* (included with your printer) into your computer's CD-ROM drive. The CD starts automatically. You can also download the latest drivers from our Web site (www.monarch.com).
- 2. Select Drivers & Utilities.
- 3. Select NiceLabel & Windows® Drivers, then click Run. If prompted to allow this software to run, click Run again. You see



- 4. Click Install Drivers.
- 5. Click Next>.
- 6. Select "I accept the terms in the license agreement" and click Next>.



USB mini-B shown

📥 Selecting the printer	×
Select Printer Please select the manufacture	r and printer you want to install.
Select the manufacturer and model printer came with a driver diskette, c your printer documentation for a cor	of your printer. If the driver is in a different folder or your dick <change location="">. If your printer is not listed, consult mpatible printer.</change>
Manufacturers:	Printers:
Avery Monarch	Monarch 9416 300dpi Monarch 9416 XL 203dpi Monarch 9416 TT 2 XL 203dpi Monarch 9416 TT 3 XL 203dpi Monarch 9433 Monarch 9446 Monarch 9460 Monarch 9490 Monarch 9493
	Exit Help < Previous Next >

- 7. Select Monarch as the Manufacturer.
- 8. Scroll until you see Monarch 9493 under Printers, and click to select.
- 9. Click Next>.

-miler opuons		1
Please select port, p	printer name and language.	C
Enter the name for your p done, select <finish> to ir</finish>	rinter. Also, select the port your printe istall the printer and add an icon to t	er is connected to. When you a ne Printers folder.
Driver version:	4.5.11	
Printer <u>n</u> ame:	Monarch 9493	
Available ports:		
USB001		Add TCP/IP Port
Microsoft Documents and	t Imaging Writer Port:	
COM1:		Delete Port
UUMZ:	<b>•</b>	
COM3:		
COM3:	printer as the Windows default printe	er.

- 10. Select the first available USB port, for example, USB001, then click Finish.
- **11.** When the installation is complete, exit NiceLabel.

The printer is now ready to receive data through the USB port.